


Using Windows Movie Maker. (page 1)

Open Windows Movie Maker by [1] clicking [Start] [2] Choose [All Programs] [3] move to [Accessories], when the next selection opens [4] choose [Entertainment] then click [5] Windows Movie Maker.



[6] [Import video] from your video folder. Can also [Capture from video] (digital camera).




Your video will be imported and made into chapters for easy editing.

Using Windows Movie Maker. (page 2)


The images are divided into chapters as shown below. You can select all chapters by following the instructions in the red text window.

Choose any one and a preview will display in the picture window. Click play to view its contents. Drag & Drop your selection to [Show Timeline].

You can work with this Show Timeline quite easily but for fine editing follow the text on page (3).



Select your video chapters by clicking first video clip, hold down the shift key and click last clip. Drag them to the [Show Timeline].



Left click the small slider to adjust volume.

Clicking the icon opens the [Audio Levels] slider. Move slider to adjust sound level.



Clicking on the microphone icon beside the volume adjusting icon you can add narration. Narrating is as easy as talking about what you see in the video as it happens. Movie Maker provides an interface to all the necessary components of Windows for narrating audio.

Using the basic editing in the above you can select individual chapters and Drag & Drop then in to new locations.

Adjust the volume of your sound track, add your transitions in-between chapters, add titles and ending credits. See page (6).

Using Windows Movie Maker. (page 3)


Clicking the Show Timeline icon changes the timeline for finer editing.



Right click the sound track (7) and a selection menu opens.

From here you can choice (8) change the [Volume], [Mute] the sound track, [Fade In] or [Fade Out]

Using Windows Movie Maker. (page 4)




Adding video transitions between chapters, select [**View video transitions**]. Move the slider close to the position to insert the transition choose one to suit the story and Drag & Drop into the transition line.

Note: Transitions can only be applied in between chapters or a break in the timeline. To fine tune your transition and place it within a chapter. Select the section of video and click on this icon to [Split] a video clip into two clips.

You can now place your transition in between the Split.

When the movie is made all Splits and chapters a joined into one video.




Split icon is on the player button bar.

The [Split] editing button is also used to remove or delete any part of the video you don't want. This does not affect the original video file.


Using Windows Movie Maker. (page 5)

To add background music, click **[Import audio or music]**. A folder will open with your music files. Click the one you want and it will be placed in the [Collection] list as shown below. Select the music and Drag & Drop to [Audio/Music] timeline. You can change the Volume of the background music by following Items (7) and (8), page (3) but right click [Audio/Music] timeline.




Using Windows Movie Maker. (page 6)

To make titles or credits for you video click item **[Make titles or credits]**.



<p>Where do you want to add a title?</p> <p>Add title at the beginning of the movie.</p> <p>Add title before the selected clip in the timeline.</p> <p>Add title on the selected clip in the timeline.</p> <p>Add title after the selected clip in the timeline.</p> <p>Add credits at the end of the movie.</p> <p>Cancel</p>	<p>To add a title click on one of the Add options in the, [Where do you want to add a title?]</p> <p>Selecting one of the options takes you to a new menu where you enter your title. Change the way it displays also change the background colour and font style.</p>
---	---

Using Windows Movie Maker. (page 7)



3. Finish Movie

- Save to my computer
- Save to CD
- Send in e-mail
- Send to the Web
- Send to DV camera


Movie Making Tips

How to capture video

Choices on the left in Windows Movie Maker, item 3 [Finish Movie].

The best choice is to [Save to my computer].

Clicking the option opens the save wizard.



Save Movie Wizard

Movie Setting

Select the setting you want to use to save your movie. The setting you select determines the quality and file size of your saved movie.

Best quality for playback on my computer (recommended)

Best fit to file size: 42 MB

Other settings: DV-AVI (PAL)

Show fewer choices:

- Video for Pocket PC (218 Kbps)
- Video for Pocket PC (143 Kbps)
- Video for Pocket PC (Full screen 218 Kbps)
- High quality video (large)
- High quality video (small)
- Video for local playback (2.1 Mbps)
- Video for local playback (1.5 Mbps)
- Video for LAN (1.0 Mbps)
- Video for LAN (768 Kbps)
- Video for broadband (512 Kbps)
- Video for broadband (340 Kbps)
- Video for broadband (150 Kbps)
- Video for DSLN (48 Kbps)
- Video for dial-up access (38 Kbps)

Setting details:

File type: Audio-Video

Bit rate: 30.0 Mbps

Display size: 720 x 480

Aspect ratio: 4:3

Frames per second: 25

Estimated disk space available on drive C: 67.10 GB

< Back Next > Cancel

In the Wizard options click other settings.

Click on the pull down options.

Select **DV-AVI (PAL)**

This give the best video display and can also be loaded into Memories On TV.

Click the [Next] button and follow the Wizard prompts to make your movie.
Remember if its a large video it will take up a lot of drive space and take time to compile.